


Starmax Bluetooth SDK Description

1. Access method

Import the sdk into the project libs directory



build.sdk format

```
sourceSets {  
    main  
        { ...other directory  
            structures jniLibs.srcDirs = ['src/main/libs']  
        }  
}  
  
dependencies {  
    //OTA library  
    implementation fileTree(dir: 'src/main/libs', include: ['*.jar','*.aar'])  
}
```

2. Permissions used

Bluetooth permissions:

```
android.permission.BLUETOOTH  
android.permission.BLUETOOTH_ADMIN  
android.permission.BLUETOOTH_CONNECT  
android.permission.BLUETOOTH_ADVERTISE
```

Location permission (required by BLE):

```
android.permission.ACCESS_FINE_LOCATION
```

Search permissions:

```
android.permission.BLUETOOTH_SCAN
```

Storage permissions:

```
android.permission.MANAGE_EXTERNAL_STORAGE  
android.permission.WRITE_EXTERNAL_STORAGE  
android.permission.READ_EXTERNAL_STORAGE
```

Network permissions:

```
android.permission.INTERNET
```

Keep the service in the foreground:

```
android.permission.FOREGROUND_SERVICE
```

3. Attributes used in AndroidManifest.xml

```
<uses-feature  
    android:name="android.hardware.bluetooth_le" android:required="true"/  
>
```

Add in application

```
<application  
    android:requestLegacyExternalStorage="true">  
</application>
```

Need to enable service

```
<service  
    android:name="com.realsil.sdk.dfu.DfuService"  
    android:exported="false">  
</service>
```

4. Returned data structure

```

class StarmaxMapResponse(obj: Map<String, Any?>?, type: NotifyType) :
    StarmaxNotifyResponse<Map<String, Any?>>(obj, type){

}

class class StarmaxProtobufResponse(obj: ByteArray, type: NotifyType) : StarmaxNotifyResponse<ByteArray>(obj,
type) {}(val obj: Map<String,Any?
>,val type: NotifyType){

}

```


Attribute Description

obj The message body returned, the structure is of Map type, and the substructure contains Map or ArrayList type

type The type of message returned

5. Interface usage

5.1 Use the flow chart:



5.2 In the Bluetooth system callback function `onCharacteristicChanged()`, pass the Bluetooth packet replied by the device to the SDK:

```
val response = MapStarmaxNotify.instance.notify(byteArray) if(response.type == NotifyType.CrcFailure){ //Handle
crc check error

    return
}

if(response.type == NotifyType.Failure){ //Handle error

    return
}

//Start processing the response below
```

5.3 Use SDK to encapsulate the data sent to the device:

```
//Such as pairing instructions, other instructions can be found in StarmaxSend

val data : ByteArray = StarmaxSend().pair()
```

6. Description of each command and return parameter:

The receiving segment is json for demonstration purposes. It is actually a combination of HashMap and ArrayList. For status codes, refer to paragraph 7.

6.1Pairing instructions:

request

```
SendmaxSend().pair()
```

response

type:

```
NotifyType.Pair
```

obj:

```
{
    "status": 0, "pair_status":
    0
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	

Fields	property	illustrate	enumerate
pair_status	Int	Pairing code	1: Confirm, 0: Cancel

6.2. Device status (bidirectional):

6.2.1 Get device status:

request

```
SendmaxSend().getState()
```

response

type:

NotifyType.GetState

obj:

```
{
  "status": 0,
  "time_format": 0,
  "unit_format": 0,
  "temp_format": 0,
  "language":0,
  "backlighting":0,
  "screen":0,
  "wrist_up":0
}
```

6.2.2 Set device status:

request

```
SendmaxSend().setState(
  timeFormat: Int,
  unitFormat: Int,
  tempFormat: Int,
  language: Int,
  backlighting: Int,
  screen: Int,
  wristUp: Boolean
)
```

response

type:



NotifyType.SetState

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	Property Description Enumeration	
status	Int	Status Code
time_format	Int	Time system 0: 24-hour system, 1: 12-hour system
unit_format	Int	Metric and Imperial 0: Metric, 1: Imperial
temp_format	Int	Temperature system 0: Celsius, 1: Fahrenheit
language	Int	Language 0 Simplified Chinese, 1 Traditional Chinese, 2 English, 3 Russian, 4 French, 5 Spanish, 6 German, 7 Japanese, 8 Italian, 9 Korean 10, Dutch, 11 Thai
backlighting	Int	Backlight Length (seconds) For single Bit)
screen	Int	Screen Bright Degree (hundred Percentage)
wrist_up	Boolean	Raise your hand to light up switch

6.3. Find device (bidirectional):

6.3.1 Find device:

requestŷ

```
SendmaxSend().findPhone(isFind:Boolean)
```

no responseŷ

6.3.2 Find your phone:

no requestŷ

responseŷ

type:

NotifyType.FindPhone

obj:

```
{  
  "is_find": true,  
}
```

Field Description:

Fields	property	illustrate	enumerate
isFind	Boolean search method		true: search, false: stop searching

6.4, Photo control (bidirectional):

6.4.1ŷ Mobile phone control equipment:

requestŷ

```
SendmaxSend().cameraControl(cameraControlType: CameraControlType)
```

no responseŷ

6.4.2 Device control mobile phone:

no requestŷ

responseŷ

type:

NotifyType.CameraControl

obj:


```
{
  "type": CameraControlType.CameraIn
}
```

Field Description:

Fields	property	Description Enumeration
cameraControlType	CameraControlType controller	CameraIn: Enter the camera interface CameraExit: Exit the camera interface TakePhoto: Shake to take photos

6.5Incoming call control (two-way):

6.5.1 Mobile phone control equipment:

request

```
SendmaxSend().phoneControl(callControlType: CallControlType, number:
String,isNumber: Boolean)
```

no response

6.5.2 Device control mobile phone:

no request

response

type:

NotifyType.PhoneControl

obj:

```
{
  "type": "HangUp",
  "value":"13700000000"
}
```

Field Description:

Fields	property	illustrate	enumerate
--------	----------	------------	-----------

Fields	property	illustrate	enumerate
callControlType CallControlType or String Control method HangUp: hang up			Answer: Answer Incoming: Incoming Exit: Outgoing call
number	String	Name or mobile phone number	
isNumber	Boolean	Is it a mobile phone number?	
value	String	Same as number	

6.6Get battery power command:

request

```
SendmaxSend().getPower()
```

response

type:

```
NotifyType.Power
```

obj:

```
{
  "status": 0,
  "power": 75,
  "is_charge":false
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
power	Int	Power	
is_charge	Boolean	Is it charging?	

6.7. Get version information:

request

`SendmaxSend().getVersion()`

response

type:

`NotifyType.Version`

obj:

```
{
  "status": 0,
  "version": "v1.0.1",
  "ui_version": "v1.0.1",
  "buffer_size": "4000",
  "lcd_width": "240",
  "lcd_height": "280",
  "screen_type": 1,
  "model": "X01G001",
  "ui_force_update": false,
  "ui_support_differential_upgrade": false,
  "support_sugar": false,
  "protocol_version": "v1.0.1"
}
```

Field Description:

Fields	Attribute Description			enumerate
status	Int	Status Code		
version	String Firmware version number			
ui_version	String ui version number			
buffer_size	String Device buffer size			
screen_type	Int	Screen type	0: round screen, 1: Square Screen	
model	String Equipment batch number			
ui_force_update	Boolean UI force upgrade			

Fields	Attribute Description	enumerate
ui_support_differential_upgrade	Boolean Whether ui supports differential upgrade	upgrade
support_sugar	Boolean whether blood sugar is supported	
protocol_version	String protocol version	

6.8. Set time and time zone:

requestÿ

```
SendmaxSend().setTime()
```

responseÿ

type:

NotifyType.SetTime

obj:

```
{
  "status": 0
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	

6.9. Set user information:

requestÿ

```
SendmaxSend().setUserInfo(sex: Int, age: Int, height: Int, weight: Int)
```

responseÿ

type:

NotifyType.SetUserInfo

obj:

```
{
  "status": 0
}
```

Field Description:

Fields	Attribute Description		enumerate
status	Int	Status Code	
sex	Int	gender	0: Female, 1: Male
age	Int	age	
height	Int	Height (in cm)	
weight	Int	Weight (unit: 0.1 KG)	

6.10. One-day movement target instruction (bidirectional):

6.10.1ÿGet the daily exercise target instruction:

requestÿ

```
SendmaxSend().getGoals()
```

responseÿ

type:

```
NotifyType.GetGoals
```

obj:

```
{
  "status": 0,
  "steps": 100,
  "heat": 100,
  "distance": 100
}
```

6.10.2 Set device status:

request

```
SendmaxSend().setGoals(  
    steps: Int,  
    heat: Int,  
    distance: Int  
)
```

response

type:

 *NotifyType.SetGoals*

obj:

```
{  
    "status": 0,  
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
steps	Int	Step Target	
heat	Int	Calorie goal (kcal)	
distance	Int	Distance to target (km)	

6.11. Get current device health data:

request

```
SendmaxSend().getHealthDetail()
```

response

type:

 *NotifyType.HealthDetail*

obj:

```
{
```

```
"status": 0,
"total_steps": 100,
"total_heat": 100,
"total_distance": 100,
"total_sleep":8122,
"total_deep_sleep":7000,
"total_light_sleep":1122,
"current_heart_rate":80,
"current_fz":100,
"current_ss": 80,
"current_blood_oxygen": 100,
"current_pressure": 30,
"current_met": 3,
"current_mai":76,
"current_temp": 30,
"current_blood_sugar":56,
"is_wear":1
```

}

Field Description:

Fields	Genus Sexual Description	Pieces Raise
status	Int status code	
total_steps	Int total steps	
total_heat	Int Total calories (kcal)	
total_distance	Int Total distance (km)	
total_sleep	Int Total sleep (minutes)	
total_deep_sleep	Int Deep sleep (minutes)	
total_light_sleep	Int Light sleep (minutes)	
current_heart_rate	Int Heart rate (beats/minute)	
current_fz	Int Diastolic blood pressure	
current_ss	Int Systolic blood pressure	
current_blood_oxygen	Int Blood oxygen saturation	
current_pressure	Int Pressure	

Fields	Attribute Description	enumerate
current_met	Int Meituo	
current_may	Int MAI	
current_temp	Int temperature (0.1 degrees Celsius)	
current_blood_sugar	Int Blood sugar (0.1)	
is_wear	Int whether to wear, 1: wearing, 0: off the wrist, (-1/255): not effect	

6.12, Health data detection switch (bidirectional):

6.12.1Get health data detection switch:

request

SendmaxSend().getHealthOpen()

response

type:

NotifyType.GetHealthOpen

obj:

```
{
  "status": 0,
  "heart_rate": true,
  "blood_pressure": true,
  "blood_oxygen": true, "pressure":
  true,
  "temp": true,
  "blood_sugar":true
}
```

6.12.2 Set the health data detection switch:

request


```
SendmaxSend().setHealthOpen(  
    heartRate: Boolean,  
    bloodPressure: Boolean,  
    bloodOxygen: Boolean,  
    pressure: Boolean,  
    temp: Boolean,  
    bloodSugar:Boolean  
)
```

response

type:

NotifyType.SetHealthOpen

obj:

```
{  
    "status": 0,  
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
heart_rate	Boolean	Heart rate switch	
blood_pressure	Boolean	Blood pressure switch	
blood_oxygen	Boolean	Blood oxygen switch	
pressure	Boolean	Pressure switch	
temp	Boolean	Temperature switch	
blood_sugar	Boolean	Blood sugar switch	

6.13. Restore factory settings:

request

```
SendmaxSend().reset()
```

response

type:

 *NotifyType.Reset*

obj:

```
{
  "status": 0
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	

6.14. Heart rate detection interval and range (bidirectional):

6.14.1 Get the heart rate detection interval and range:

request

```
SendmaxSend().getHeartRateControl()
```

response

type:

 *NotifyType.GetHeartRate*

obj:

```
{
  "status": 0,
  "start_hour": 0,
  "start_minute": 0, "end_hour":
0, "end_minute":0,
  "period":0,
  "alarm_threshold":0
}
```

6.14.2 Set the heart rate detection interval and range:

request

```
SendmaxSend().setHeartRateControl(  
    startHour: Int,  
    startMinute: Int,  
    endHour: Int,  
    endMinute: Int, period:  
    Int,  
    alarmThreshold: Int  
)
```

response

type:

 *NotifyType.SetHeartRate*

obj:

```
{  
    "status": 0,  
}
```

Field Description:

Fields	Attribute Description		enumerate
status	Int	Status Code	
start_hour	Int	Start Hour	
start_minute	Int	Start minute	
end_hour	Int	End Hour	
end_minute	Int	End Minute	
period	Int	Cycle (minutes)	
alarmThreshold	Int	Alarm threshold (percentage)	

6.15 Frequently used contacts (two-way):

Note: The device can store up to 20 frequently used contacts.

6.15.1 Get frequently used contacts:

request

```
SendmaxSend().getContacts()
```

response

type:

NotifyType.GetContact

obj:

```
{
  "status": 0,
  "contacts": [
    {
      "name": "Zhang San",
      "phone": "123123123122"
    },
    {
      "name": "Li Si",
      "phone": "123123123422"
    }
  ]
}
```

6.15.2 Set up common contacts:

request

```
SendmaxSend().setContacts(contacts: List<Contact>)
```

response

type:

NotifyType.SetContact

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
contacts	List	Contacts array	
contact.name	String	Name	
contact.phone	String	Telephone	

6.16 Emergency Contact (two-way):

Note: The device can store up to 3 emergency contacts

6.16.1ÿ Obtain emergency contacts:

requestÿ

SendmaxSend().getSos()

responseÿ

type:

NotifyType.GetSos

obj:

```
{
  "status": 0,
  "contacts":[
    {
      "name":"Zhang San",
      "phone":"123123123122"
    },
    {
      "name":"Li Si",
      "phone":"123123123422"
    }
  ]
}
```

6.16.2 Set up common contacts:

request

```
SendmaxSend().setSos(contacts: List<Contact>)
```

response

type:

NotifyType.SetSos

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
contacts	List	Contacts array	
contact.name	String	Name	
contact.phone	String	Telephone	

6.17, Do Not Disturb Mode (Two-Way):

6.17.1 Get the Do Not Disturb mode:

request

```
SendmaxSend().getNotDisturb()
```

response

type:

NotifyType.GetNotDisturb

obj:

```
{
  "status": 0,
  "all_day_on_off": false,
  "on_off": false,
  "start_hour": 0,
  "start_minute": 0,
  "end_hour": 23,
  "end_minute": 59
}
```

6.17.2 Set Do Not Disturb mode:

request

```
SendmaxSend().setNotDisturb(
    onOff: Boolean,
    allDayOnOff: Boolean,
    startHour: Int,
    startMinute: Int,
    endHour: Int,
    endMinute: Int
)
```

response

type:

NotifyType.SetNotDisturb

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
all_day_on_off	Boolean	Do Not Disturb All Day	
on_off	Boolean	Scheduled Do Not Disturb	
start_hour	Int	Start Hour	

Fields	property	illustrate	enumerate
start_minute	Int	Start minute	
end_hour	Int	End Hour	
end_minute	Int	End Minute	

6.18, Alarm clock (two-way):

6.18.1ÿ Get the alarm clock:

requestÿ

```
SendmaxSend().getClock()
```

responseÿ

type:

```
NotifyType.GetClock
```

obj:

```
{
  "status": 0,
  "clock_list":[
    {
      "hour":0,
      "minute":0,
      "onOff":true,
      "repeats":[true,true,true,true,true,true,true],
      "type":0
    }
  ]
}
```

6.18.2 Setting the alarm:

requestÿ

```
SendmaxSend().setClock(clocks: List<Clock>)
```


response

type:

NotifyType.SetClock

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
clock_list	List	Alarm List	
clock.hour	Int	Hour	
clock.minute	Int	minute	
clock.onOff	Boolean alarm switch		
clock.repeats	List	Weekly repeat switch (Sunday is the first day)	
clock.type	Int	Type (no meaning yet)	

6.19, Sedentary reminder (two-way):

6.19.1 Get sedentary reminder:

request

```
SendmaxSend().getLongSit()
```

response

type:

NotifyType.GetLongSit

obj:

```
{  
  "status": 0,  
  "on_off": false,  
  "start_hour": 0,  
  "start_minute": 0,  
  "end_hour": 23,  
  "end_minute": 59,  
  "interval": 60  
}
```

6.19.2 Set sedentary reminder:

request

```
SendmaxSend().setLongSit(  
  onOff: Boolean,  
  startHour: Int,  
  startMinute: Int,  
  endHour: Int,  
  endMinute: Int,  
  interval: Int  
)
```

response

type:

NotifyType.SetLongSit

obj:

```
{  
  "status": 0,  
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
on_off	Boolean	Reminder switch	
start_hour	Int	Start Hour	
start_minute	Int	Start minute	

Fields	property	illustrate	enumerate
end_hour	Int	End Hour	
end_minute	Int	End Minute	
interval	Int	Reminder interval (minutes)	

6.20, Drink water reminder (two-way):

6.20.1 Get water drinking reminder:

request

```
SendmaxSend().getDrinkWater()
```

response

type:

NotifyType.GetDrinkWater

obj:

```
{
  "status": 0,
  "on_off": false,
  "start_hour": 0,
  "start_minute": 0,
  "end_hour": 23,
  "end_minute": 59,
  "interval": 60
}
```

6.20.2 Set a water drinking reminder:

request

```
SendmaxSend().setDrinkWater(
  onOff: Boolean,
  startHour: Int,
  startMinute: Int,
  endHour: Int,
  endMinute: Int,
  interval: Int
)
```

response

type:

`NotifyType.SetDrinkWater`

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
on_off	Boolean	Reminder switch	
start_hour	Int	Start Hour	
start_minute	Int	Start minute	
end_hour	Int	End Hour	
end_minute	Int	End Minute	
interval	Int	Reminder interval (minutes)	

6.21. Push Messages:

request

`SendmaxSend().sendMessage(messageType: MessageType, title: String, content: String)`

response

type:

`NotifyType.SendMessage`

obj:

```
{
  "status": 0
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
messageType	MessageType	Message type Refer to the MessageType enumeration type	
title	String	title	
content	String	content	

6.22. Push weather:

requesty

```
SendmaxSend().setWeather(weatherDays: List<WeatherDay>)
```

responsey

type:

```
NotifyType.SetWeather
```

obj:

```
{
  "status": 0
}
```

Field Description:

Fields	Genus sex	explain Ming Enumeration
status	Int Status	code

Fields	property	Description Enumeration
weatherDays	List Weather list	(next 4 days, including today)
weatherDay.temp	Int Current temperature	
weatherDay.maxTemp	Int Maximum temperature	
weatherDay.minTemp	Int minimum temperature	
weatherDay.windSpeed	Int wind speed	
weatherDay.dampness	Int Humidity	
weatherDay.seeing	Int Meter	
weatherDay.airQuality	Int Air Quality	1 Excellent, 2 Good, 3 Poor
weatherDay.type	Int Type	1. Light rain, 2. Moderate rain, 3. Heavy rain, 4. Overcast, 5. Cloudy, 6. Sunny, 7. Haze, 8. Typhoon, 9. Thunderstorm, 10. Hail, 11. Light snow, 12. Moderate snow, 13. Heavy snow, 14. Sleet, 15. Sandstorm, 16. Snow and hail, 17. Strong wind, 18. Strong wind, 19. Light wind, 20. Tornado, 21. Tropical storm, 22. Thunderstorm, 23. Severe thunderstorm, 24. Unkn

6.23, Music control (two-way):

6.23.1App control device:

requestÿ

```
SendmaxSend().musicControl(playState: Int,volPercent: Int,ratePercent:
Int,musicTitle: String,lyric:String)
```

no responseÿ

Field Description:

Fields	property	illustrate	enumerate
playState	Int	Player Status	0 Pause 1 Play
volPercent	Int	Volume Percentage	
ratePercent	Int	Song Progress	
musicTitle	String	Song Title	
lyric	String	lyrics	

6.23.2 Device Control App:

no requestÿ

responseÿ

type:

NotifyType.MusicControl

obj:

```
{
  "type": MusicControlType.Play,
}
```

Field Description:

Field properties	illustrate	enumerate
type	MusicControlType	Control command Play: Play Stop: Stop playing Continue: Continue playing Previous: Next: AddVol:Volume+ SubVol:Volume-

6.24, Event reminder (two-way):

6.24.1. Get event reminders:

request

```
SendmaxSend().getEventReminder()
```

response

type:

NotifyType.GetEventReminder

obj:

```
{
  "status": 0,
  "event_reminders": [ {
    "year": 2023,
    "month": 2,
    "day": 6,
    "hour": 17,
    "minute": 26,
    "content": "Going out with friends",
    "remind_type": 1,
    "repeat_type": 1, "repeats":
    [true,false,false,false,false,false,true]
  }
]
```

6.24.2 Set event reminder:

request

```
SendmaxSend().setEventReminder(reminders: List<EventReminder>)
```

response

type:

NotifyType.SetEventReminder

obj:


```
{
    "status": 0,
}
```

Field Description:

Fields	Attribute Description	enumerate
status	Int status code	
event_reminders	List Event List	
event_reminder.year	Int year	
event_reminder.month	Int	moon
event_reminder.day	Int	day
event_reminder.hour	Int hour	
event_reminder.minute	Int Minutes	
event_reminder.content	String content	
event_reminder.remind_type	Int reminder type	1ÿ2ÿ3ÿ4
event_reminder.repeat_type	Int Repeat type	1. Single 2: Day 3: Week 4: month 5: year
event_reminder.repeats	List repeats every week, Monday For the first day	

6.25. Synchronous motion data:

requestÿ

```
SendmaxSend().getSportHistory()
```

Note: Get one record at a time. You can call this interface multiple times for multiple records.

responseÿ

type:

NotifyType.SportHistory

obj:

```
{  
  "status": 0,  
  "sport_length":1,  
  "current_sport_id":1,  
  "current_sport_data_length":1000,  
  "year":2023,  
  "month":2,  
  "day":6,  
  "hour":19,  
  "minute":16,  
  "second":30,  
  "type":1,  
  "steps":1000,  
  "distance":1000,  
  "speed":1,  
  "calorie":1000,  
  "pace_time":300,  
  "step_frequency":10,  
  "heart_rate_length":3,  
  "heart_rate_list":[100,90,80]  
}
```

Field Description:

Fields	Attribute Description	enumerate
status	Int status code	
sport_length	Int total number of movements	
current_sport_id	Int Current sport ID	
current_sport_data_length	Int Current motion data length	
year	Int year	
month	Int month	
day	Int day	
hour	Int hour	
minute	Int Minutes	
second	Int seconds	
type	Int Sports type: Refer to 100 sports types	

Fields	Attribute Description	enumerate
steps	Int total number of steps	
distance	Int Total distance (m)	
speed	Int speed (m/s)	
heat	Int Calories (calories)	
pace_time	Int pace	
step_frequency	Int Cadence	
heart_rate_length	Int heart rate data length	
heart_rate_list	List heart rate data array	

6.26, Synchronous pedometer sleep:

request

```
SendmaxSend().getStepHistory(calendar:Calendar)
```

response

type:

NotifyType.StepHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "step_list":[
    {
      "hour":16,
      "minute":8,
      "data_type":1,
      "steps":1000,
      "calorie":1000,
      "distance":1000
    }
  ]
}
```

```
    ],
    "sleep_list":[
      {
        "hour":16,
        "minute":8,
        "data_type":2,
        "sleep_status":1
      }
    ]
  }
}
```

Field Description:

Fields		Genus
		Sex Description Enumeration
status	Int status code	
interval	Int Sampling Room	
year	Int year	
month	Int month	
day	Int day	
step.hour,sleep.hour	Int hour	
step.minute,sleep.minute	Int minute	
step_list	List Step List	
sleep_list	List Sleep List	
step.steps	Int number of steps	
step.distance	Int distance (rice)	
step.calore	Int Calories (Card)	
sleep.sleep_status	Int Sleep status	1: Start to fall asleep, 2: Light sleep, 3: Deep sleep, 4: Awake, 5: Rapid eye movement, 129: beginning to fall asleep (nap), 130: light Sleep (nap), 131: Deep sleep (nap), 132: Awake (nap) Sleep), 133: Rapid Eye Movement (nap)

request

```
SendmaxSend().getHeartRateHistory(calendar:Calendar)
```

response

type:

NotifyType.HeartRateHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "heart_rate_list":[
    {
      "hour":16,
      "minute":8,
      "heart_rate":100
    }
  ],
}
```

Field Description:

Fields	Attribute Description		enumerate
status	Int	Status Code	
interval	Int	Sampling interval	
year	Int	Year	
month	Int	month	
day	Int	day	
data_length	Int	Total data length	
heart_rate_list	List	Heart rate array	

Fields	Attribute Description		enumerate
heart_rate.hour	Int	Hour	
heart_rate.minute	Int	minute	
heart_rate.heart_rate	Int	Heart rate	

6.28. Synchronous blood pressure data:

request

```
SendmaxSend().getBloodPressureHistory(calendar:Calendar)
```

response

type:

NotifyType.BloodPressureHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "blood_pressure_list":[
    {
      "hour":16,
      "minute":8,
      "ss":100,
      "fz":80
    }
  ],
}
```

Field Description:

Fields	Attribute Description		enumerate
status	Int	Status Code	
interval	Int	Sampling interval	

Fields	Attribute Description		enumerate
year	Int	Year	
month	Int	moon	
day	Int	day	
data_length	Int	Total data length	
blood_pressure_list	List blood pressure array		
blood_pressure.hour	Int	Hour	
blood_pressure.minute	Int	minute	
blood_pressure.ss	Int	Systolic blood pressure	
blood_pressure.fz	Int	Diastolic blood pressure	

6.29. Synchronous blood oxygen data:

request

```
SendmaxSend().getBloodOxygenHistory(calendar:Calendar)
```

response

type:

NotifyType.BloodOxygenHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "blood_oxygen_list":[
    {
      "hour":16,
      "minute":8,
      "blood_oxygen":100
    }
  ],
}
```

```
}
```

Field Description:

Fields	Attribute Description	enumerate
status	Int status code	
interval	Int sampling interval	
year	Int	Year
month	Int	moon
day	Int	day
data_length	Int total data length	
blood_oxygen_list	List blood oxygen array	
blood_oxygen.hour	Int hour	
blood_oxygen.minute	Int Minutes	
blood_oxygen.blood_oxygen	Int blood oxygen	

6.30, Synchronous pressure data:

request

```
SendmaxSend().getPressureHistory(calendar:Calendar)
```

response

type:

NotifyType.PressureHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
```



```
    "pressure_list":[
      {
        "hour":16,
        "minute":8,
        "pressure":60
      }
    ],
  }
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
interval	Int	Sampling interval	
year	Int	Year	
month	Int	moon	
day	Int	day	
data_length	Int	Total data length	
pressure_list	List	Pressure Array	
pressure.hour	Int	Hour	
pressure.minute	Int	minute	
pressure.pressure	Int	pressure	

6.31. Synchronize Metadata:

request

```
SendmaxSend().getMetHistory(calendar:Calendar)
```

response

type:

NotifyType.MetHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "met_list":[
    {
      "met":3
    }
  ],
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
interval	Int	Sampling interval	
year	Int	Year	
month	Int	moon	
day	Int	day	
data_length	Int	Total data length	
met_list	List	Meta array	
with.with	Int	Meto	

6.32. Synchronize temperature data:

request

SendmaxSend().getTempHistory(calendar:Calendar)

response

type:

NotifyType.TempHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "temp_list":[
    {
      "hour":16,
      "minute":8,
      "temp":365
    }
  ],
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
interval	Int	Sampling interval	
year	Int	Year	
month	Int	moon	
day	Int	day	
data_length	Int	Total data length	
temp_list	List	Temperature array	
temp.hour	Int	Hour	
temp.minute	Int	minute	
temp.temp	Int	Celsius	

6.33. Synchronous MAI:

requestj

```
SendmaxSend().getMaiHistory(calendar:Calendar)
```

response

type:

NotifyType.Mai

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "mai_list":[
    {
      "mai":50
    }
  ],
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
interval	Int	Sampling interval	
year	Int	Year	
month	Int	moon	
day	Int	day	
data_length	Int	Total data length	
may_list	List	MAI Array	
more.more	Int	MIA	

6.34. Validity date of synchronized historical data:

request

```
StarmaxSend().getValidHistoryDates(historyType: HistoryType)
```

response

type:

NotifyType.ValidHistoryDates

obj:

```
{
  "status": 0,
  "valid_history_dates": [
    {
      "year": 2023,
      "month": 2,
      "day": 7
    }
  ],
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
interval	Int	Sampling interval	
year	Int	Year	
month	Int	moon	
day	Int	day	
data_length	Int	Total data length	
may_list	List	MAI Array	
more.more	Int	MIA	

6.35. Synchronize blood sugar data:

requestÿ

```
SendmaxSend().getBloodOxygenHistory(calendar:Calendar)
```

responseÿ

type:

NotifyType.BloodSugarHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "blood_oxygen_list":[
    {
      "hour":16,
      "minute":8,
      "blood_sugar":64
    }
  ],
}
```

Field Description:

status	Int status code	
interval	Int	Sampling interval
year	Int	Year
month	Int	moon
day	Int	day
data_length	Int total data length	
blood_sugar_list	List blood sugar array	
blood_sugar.hour	Int	Hour

status	Int status code	
blood_sugar.minute	Int	minute
blood_sugar.blood_sugar	Int	blood sugar

6.36 Switch dial:

request

```
SendmaxSend().switchDial(dialId: Int)
```

response

type:

```
NotifyType.SwitchDial
```

obj:

```
{
  "status": 0
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
dialId	Int	Dial ID	

6.37. Synchronize dial data:

request

```
SendmaxSend().getDialInfo()
```

response

type:

```
NotifyType.DialInfo
```

obj:

```
{
  "status": 0,
  "dial_list": [
    {
      "is_selected": 16,
      "dial_id": 5001,
    }
  ],
}
```

Field Description:

status	Int	Status Code
dial_list	List	Watch face array
dial.is_selected	Int	1 is selected, 0 is not selected
dial.dial_id	Int	Dial ID

6.38, Push weather (7 days):

GTS7 Applicable

request

```
SendmaxSend().setWeatherSeven(cityName: String,weatherDays:
List<WeatherDay>)
```

response

type:

```
NotifyType.SetWeather
```

obj:

```
{
  "status": 0
}
```


Field Description:

Fields	property	explain	Ming Enumeration
status	Int Status	code	
cityName	String City	name	
weatherDays	List Weather	List (not yet He 4 sky, include now sky)	
weatherDay.temp	Int current	temperature	
weatherDay.maxTemp	Int Highest	temperature	
weatherDay.minTemp	Int minimum	temperature	
weatherDay.windSpeed	Int wind speed		
weatherDay.dampness	Int Humidity		
weatherDay.seeing	Int Meter		
weatherDay.airQuality	Int Air	quality	1 Excellent, 2 Good, 3 Poor
weatherDay.type	Int type	1, light rain, 2, moderate rain, 3, heavy rain, 4, Cloudy, 5, cloudy, 6, clear, 7, foggy Haze, 8, typhoon, 9, thunderstorm, 10, ice Hail, 11, Light Snow, 12, Medium Snow, 13, Heavy Snow, 14, Sleet, 15, Sandstorm, 16, Snow and hail, 17, squall, 18, strong wind, 19. Light wind, 20. Tornado, 21. Tropical Storm, 22, Thunderstorm, 23, Severe Thunderstorm, 24. Unknown	
weatherDay.sunriseHour	Int Sunrise hour		
weatherDay.sunriseMinute	Int	Sunrise Minutes	

Fields	property	Description Enumeration
weatherDay.sunsetHour	Int	Sunset Hour
weatherDay.sunsetHour	Int	Sunset Minutes
weatherDay.moonriseHour	Int	moonrise hour
weatherDay.moonriseMinute	Int	Moonrise minute
weatherDay.moonsetHour	Int	Moonset Hour
weatherDay.moonsetMinute	Int	Moonset minute

6.39, Application Market (Bidirectional, GTS7):

6.39.1 Get the application market:

request

```
SendmaxSend().getApps()
```

response

type:

NotifyType.GetApps

obj:

```
{
  "status": 0,
  "apps": [1, 2, 3],
}
```

6.39.2 Set up the application market:

request

```
SendmaxSend().setApps(apps: List<Int>)
```

response

type:



obj:

```
{
  "status": 0,
}
```

Field Description:

Field properties		Description Enumeration
status Int		
		Status Code
apps	IntArray Application	1. Breathing training, 2. Metabolism, 3. Voice assistant, 4. Timer, 5. Stopwatch, 6. Timer, 7. Alarm clock, 8. Flashlight, 9. Find phone, 10. World clock, 11. Pomodoro, 12. Women's health, 13. Blood sugar, 14. Blood pressure
	List	

6.40, World Clock (Bidirectional, GTS7):

6.40.1. Get the world clock:

request

```
SendmaxSend().getWorldClocks()
```

response

type:



obj:

```
{
  "status": 0, "citys":
  [1,2,3],
}
```

6.40.2 Setting the world clock:

requestÿ

```
SendmaxSend().setWorldClocks(apps: List<Int>)
```

responseÿ

type:

NotifyType.SetWorldClocks

obj:

```
{  
  "status": 0,  
}
```

Field Description:

Field properties		Description Enumeration
status Int		
		Status Code
cities	IntArray	1. Beijing (GMT+8) 2. Washington (GMT-5) 3. London (GMT+0) 4. Paris (GMT+1) 5. New York (GMT-5) 6. Tokyo (GMT+9) 7. Shanghai (GMT+8) 8. Mumbai (GMT+5:30) 9. Sydney (GMT+11) 10. Los Angeles (GMT-8) 11. Moscow (GMT+3) 12. Berlin (GMT+1) 13. Rome (GMT+1) 14. Istanbul (GMT+3) 15. Cairo (GMT+2) 16. Nanjing (GMT+8) 17. Vancouver (GMT-8) 18. Chicago (GMT-6) 19. Rio de Janeiro (GMT-3) 20. Amsterdam (GMT+1) 21. Singapore (GMT+8) 22. Seoul (GMT+9) 23. Melbourne (GMT+11) 24. New Delhi (GMT+5:30) 25. Canberra (GMT+11) 26. Brasilia (GMT-3) 27. Mexico City (GMT-6) 28. Hong Kong (GMT+8) 29. Stockholm (GMT+1) 30. Barcelona (GMT+1) 31. Munich (GMT+1) Note: n supports up to 16

6.41ÿSet password and remove lock switch (two-way, GTS7):

6.41.1ÿ Get the password:

requestÿ

```
SendmaxSend().getPassword()
```

response

type:

NotifyType.GetPassword

obj:

```
{
  "status": 0,
  "password": "123456",
  "is_open": false
}
```

6.40.2 Set password:

request

SendmaxSend().setPassword(password: String,isOpen: Boolean)

response

type:

NotifyType.SetPassword

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	
password	String	password	
isOpen	Boolean	Is it open?	

6.42, Women's Health (Bidirectional, GTS7):

6.42.1. Access to Women's Health:

request

SendmaxSend().getFemaleHealth()

response

type:

NotifyType.GetFemaleHealth

obj:

```
{
  "status": 0,
  "password": "123456",
  "is_open": false
}
```

6.40.2 Setting up Women's Health:

request

SendmaxSend().setFemaleHealth(numberOfDays: Int,cycleDays: Int,lastDate: Calendar)

response

type:

NotifyType.SetFemaleHealth

obj:

```
{
  "status": 0,
}
```

Field Description:

Fields	property	illustrate	enumerate
status	Int	Status Code	

Fields	property	illustrate	enumerate
number_of_days	Int	Menstrual days	
cycle_days	Int	Menstrual cycle	
year	Int	Last year	
month	Int	Last month	
day	Int	Last day	

6.41. Synchronous sleep records:

requestŷ

```
SendmaxSend().getSleepHistory(calendar:Calendar)
```

responseŷ

type:

NotifyType.SleepHistory

obj:

```
{
  "status": 0,
  "interval":1,
  "year":2023,
  "month":2,
  "day":7,
  "data_length":2000,
  "sleep_list":[
    {
      "hour":16,
      "minute":8,
      "sleep_status":1
    }
  ],
}
```

Field Description:

Fields	Attribute Description	enumerate
status	Int status code	

Fields	Attribute Description	enumerate
interval	Int sampling interval	
year	Int year	
month	Int month	
day	Int day	
data_length	Int total data length	
sleep_list	List sleep array	
sleep_list.hour	Int hour	
sleep_list.minute	Int Minutes	
sleep_list.sleep_status	Int Sleep state 1 Beginning to fall asleep 2 Light sleep 3 Deep sleep 4 Awake	

7. Status code description:

Status Code	illustrate
0	The command code is correct
1	Command code error
2	Check code error
3	Data length error
4	Invalid data

8.100 sports modes:

type	illustrate
0	Outdoor Cycling
1	Outdoor running
2	climb mountains

type e	illustrate
3	Indoor Cycling
4	Burpees
5	tennis
6	jump rope
7	Feather Ball
8	Yoga
9	Football
10	Squat
11	Indoor Cycling
12	Outdoor Walking
13	High leg raise exercise
14	on foot
15	Walking
16	Indoor running
17	Indoor walking
18	Strength training
19	Arm strength training
20	Elliptical Machine
21	basketball
22	Leg Training
23	Stepper
24	Walker
25	Aerobics

type e	illustrate
2 6	Group Exercise
2 7	Pilates
2 8	Crossfit
2 9	Functional training
3 0	Physical training
3 1	Taekwondo
3 2	boxing
3 3	Free Fighting
3 4	karate
3 5	fencing
3 6	Orienteering
3 7	Core Training
3 8	Kickboxing
3 9	kendo
4 0	horizontal bar
4 1	parallel bars
4 2	Belly Dance
4 3	Jazz Dance
4 4	Latin Dance
4 5	Bamboo bud
4 6	Street Dance
4 7	Square Dance
4 8	Other dances

type e	illustrate
4 9	Roller skating
5 0	Martial Arts
5 1	Tai Chi
5 2	Hula Hoop
5 3	Free Movement
5 4	Racing
5 5	Frisbee
5 6	Darts
5 7	Archery
5 8	horse riding
5 9	Battle Game
6 0	Flying a kite
6 1	Tug of War
6 2	Autumn
6 3	Climbing stairs
6 4	Obstacle Race
6 5	fishing
6 6	table tennis
6 7	billiards
6 8	bowling
6 9	volleyball
7 0	Shuttlecock
7 1	Handball

type e	illustrate
7 2	baseball
7 3	softball
7 4	cricket
7 5	Rowing Machine
7 6	football
7 7	Beach Volleyball
7 8	parachute
7 9	Croquet
8 0	hockey
8 1	squash
8 2	Fuji ball
8 3	Dodgeball
8 4	skate
8 5	puck
8 6	push-up
8 7	Plank
8 8	ski
8 9	Curling
9 0	Snowmobile
9 1	Snow Sled
9 2	Sit-ups
9 3	Biathlon
9 4	skateboard

type	illustrate
95	rock climbing
96	Bungee Jumping
97	Parkour
98	BMX
99	Jumping jacks

9. Update records:

date	Version	Content
2023/4/14	1.0.2	Added blood sugar, StarmaxNotify became an abstract class and inherited MapStarmaxNotify
2023/8/21	1.0.3	Add whether the current health data is worn
2023/11/22	1.0.4	Added 100 new sports modes
2024/1/29	1.0.5	Added GTS7 weather, app store, world clock, wrist-off password, women's health, SDK is adjusted based on protobuf